

enfocus
SWITCH 2018

Switch Web Portal
Documentation

Contents

1. Copyrights.....	3
2. Using the Switch Web Portal.....	4
2.1. Signing in to the Switch Web Portal.....	4
2.2. Changing the language of the Switch Web Portal.....	5
2.3. Viewing log messages through the Switch Web Portal.....	5
2.3.1. The Messages overview.....	6
2.3.2. Filtering log messages.....	9
2.3.3. Sorting log messages.....	10
2.3.4. Exporting log messages.....	11
2.3.5. Clearing log messages.....	11
2.4. Finding Switch jobs through the Switch Web Portal.....	12
2.4.1. About job boards.....	12
2.4.2. Creating a job board.....	13
2.4.3. Managing a job board.....	14
2.4.4. Viewing and finding jobs on a job board.....	15
2.5. Managing dashboards on the Switch Web Portal.....	16
2.5.1. About dashboards and widgets.....	16
2.5.2. Creating a dashboard.....	19
2.5.3. Managing a dashboard.....	21
2.5.4. Viewing a dashboard.....	22
2.5.5. Dashboard widgets overview.....	23
2.6. Submitting and checking jobs through the Switch Web Portal.....	30
2.6.1. Setup in Switch.....	30
2.6.2. The Switch Web Portal User Interface.....	37
2.6.3. Submitting jobs through the Switch Web Portal.....	41
2.6.4. Viewing jobs through the Switch Web Portal.....	43
2.6.5. Reviewing and processing jobs through the Switch Web Portal.....	48

1. Copyrights

© 2019 Enfocus BVBA all rights reserved. Enfocus is an Esko company.

Certified PDF is a registered trademark of Enfocus BVBA.

Enfocus PitStop Pro, Enfocus PitStop Workgroup Manager, Enfocus PitStop Server, Enfocus Connect YOU, Enfocus Connect ALL, Enfocus Connect SEND, Enfocus StatusCheck, Enfocus CertifiedPDF.net, Enfocus PDF Workflow Suite, Enfocus Switch, Enfocus SwitchClient, Enfocus SwitchScripter and Enfocus Browser are product names of Enfocus BVBA.

Adobe, Acrobat, Distiller, InDesign, Illustrator, Photoshop, FrameMaker, PDFWriter, PageMaker, Adobe PDF Library™, the Adobe logo, the Acrobat logo and PostScript are trademarks of Adobe Systems Incorporated.

Datalogics, the Datalogics logo, PDF2IMG™ and DLE™ are trademarks of Datalogics, Inc.

Apple, Mac, Mac OS, Macintosh, iPad and ColorSync are trademarks of Apple Computer, Inc. registered in the U.S. and other countries.

Windows, Windows 2000, Windows 7, Windows 8, Windows 8.1, Windows 10, Windows 2008 Server, Windows 2008 Server R2, Windows Server 2012, Windows Server 2012 R2 and Windows Server 2016 are registered trademarks of Microsoft Corporation.

PANTONE® Colors displayed here may not match PANTONE-identified standards. Consult current PANTONE Color Publications for accurate color. PANTONE® and other Pantone, Inc. trademarks are the property of Pantone, Inc. ©Pantone, Inc., 2006.

OPI is a trademark of Aldus Corporation.

Monotype is a trademark of Monotype Imaging Inc. registered in the U.S. Patent and Trademark Office and may be registered in certain jurisdictions. Monotype Baseline is a trademark of Monotype Imaging Inc.

Quark, QuarkXPress, QuarkXTensions, XTensions and the XTensions logo among others, are trademarks of Quark, Inc. and all applicable affiliated companies, Reg. U.S. Pat. & Tm. Off. and in many other countries.

This product and use of this product is under license from Markzware under U.S. Patent No. 5,963,641.

Other brand and product names may be trademarks or registered trademarks of their respective holders. All specifications, terms and descriptions of products and services are subject to change without notice or recourse.

2. Using the Switch Web Portal

The Switch Web Portal allows users to access the Switch Server through a web browser. This means that users can access the Switch Server from another computer than the one that is running the Switch Server, without the need for a Switch Designer.

Currently, the following functionality is available:

- Viewing log messages issued by the Switch Server. This includes customizing the messages overview (sorting, filtering, etc) and exporting and clearing messages as required.
- Viewing and finding jobs processed by the Switch Server. This includes creating your own job board(s), which allows you to visualize the jobs present in certain flows and with certain flow stages. If you have purchased a Reporting Module license, you can use the data on these job boards to create dashboards with counters and graphs.
- Submitting and checking jobs, on condition that you have licensed the SwitchClient Module.


Note that users should be granted access via the Users pane.

The connection can be encrypted as required (HTTPS); this can be configured through the user preferences. Refer to the Switch Reference Guide (Switch preferences: Web Services).

2.1. Signing in to the Switch Web Portal

To sign in to the Switch Web Portal

1. Open a browser.
Google Chrome, Safari, Edge and Firefox are supported.
2. Enter the IP address or the hostname of the computer running the Switch Server followed by ":" and the port number for the Switch Web Portal (as set in the Switch Preferences (Web Services category)). The default port number is 51089.
For example:



A login screen appears. The first time you'll see a banner stating that cookies on the site are used to enhance the user experience.

3. In the banner, click **Accept** to allow Switch to save your preferences.
If you accept cookies, your preferences are saved by the browser. As a consequence, you don't have to set your preferences next time you sign in; they are remembered. If you click **Do not use cookies**, you can continue to work, but you will have to set your preferences again next time you log in.
4. Enter your user name and password and click **Sign in**.
The Switch Server must be running, otherwise you will not be able to sign in.

The Switch Web Portal main screen appears. What you can see and do, depends on your permissions (as configured by the Switch administrator through the Users panel).

2.2. Changing the language of the Switch Web Portal

By default the language on the Switch Web Portal is determined by your system's local settings.

To select a different language (i.e. one of the Switch languages), proceed as follows:

1. In the top right corner of the screen, click your user name.

The name displayed is your user name as defined in the Users pane in the Switch Designer.

2. Click the language of your choice.

Possible languages:

- English
- German
- French
- Japanese
- Chinese

Your choice is remembered. Next time you sign in to the Web Portal (through the same browser), the content will be displayed in the chosen language.

2.3. Viewing log messages through the Switch Web Portal

If you have the right permissions, you can view the log messages in a browser without having to open a Switch Designer. The permissions are set through the Users pane.

To view the log messages

1. Sign in to the Switch Web Portal.

See [Signing in to the Switch Web Portal](#) on page 4.

2. If the messages are not displayed, in the navigation area on the left, click  **Messages**. The most recent log messages are displayed, with a maximum of 1000 messages in total. If the autorefresh option is turned on (at the bottom of the screen), the list is automatically renewed. By default, the list is sorted chronologically, most recent messages at the top.

Remark:

- If the message text is too long to be displayed, you can turn on the **Wrap text** option.
- If you don't want to see all columns, you can hide some of them using the **Columns** option.

Both options are available in the menu that appears when you click the button  on the right, below your user name (see screenshot).

SwitchUser ▾

Element ▾	Prefix ▾	Job	...
SubmitHi...	0028S	...	...
SubmitHi...	0028Q	...	...
SubmitHi...	0028P	...	...
SubmitHi...	0028O	...	...
SubmitHi...	0028N	...	...
SubmitHi...	0028M	_001K4_...	Duplicated job with new u...
SubmitHi...	0028L	_001K3_...	Duplicated job with new u...
SubmitHi...	0028K	001K2 ...	Duplicated job with new u...

▾ Wrap text
 ... Columns
 ↑ Export messages
 — Clear messages

You can now sort the messages, filter out the messages you're not interested in, or export messages as required. Refer to [Filtering log messages](#) on page 9, [Sorting log messages](#) on page 10 and [Exporting log messages](#) on page 11.

2.3.1. The Messages overview

This topic describes the Messages overview. You can open this overview in different ways:

- Through the Switch Web Portal.
- By clicking the **Messages** button in the toolbar of the Switch Designer. Alternatively, you can press **F6** or select **View > Messages**.

Buttons and menus

The table below explains the meaning of the main buttons, labels, icons and menus in the Messages overview.

sort Type ASC × New flow 1 × SwitchUser ▾

Time ▾	Type ▾	Flow ▾	Message ▾	...
2017-01-27 15:44:18	info	New flow 1	Moved job to folder 'Folder 2'	
2017-01-27 15:44:17	info	New flow 1	Stripped unique name prefix '002WB'; resulting	
2017-01-27 15:44:17	info	New flow 1	Added unique name prefix, new name is '_002'	
2017-01-27 15:43:51	info	New flow 1	Flow 'New flow 1' was activated	
2017-01-27 15:43:51	info	New flow 1	Flow 'New flow 1' was successfully validated	

Filter returned 5 messages. Last refresh: 27/01/2017 16:11:18

autorefresh OFF

Button/menu	Description
	Shows the name of the user that logged in. If you click the icon , you'll get a menu where you can change the language and sign out as required. See Changing the language of the Switch Web Portal on page 5.  Note: If you open the Messages overview <i>from within Switch</i>, this option is not available. In that case, the Messages overview is displayed in the language of the Switch Designer.
	Opens a menu with the following options: • Wrap text: Moves text that does not fit on one line (because the column is too small) to the next line (instead of cutting it off). • Columns: Allows you to show or hide columns as required (and afterwards reset them as required). • Export messages: Allows you to export the <i>filtered</i> log messages to a .csv file. You can either open the file or save it locally. • Clear messages: Allows you to remove all log messages from the log database. Note that there is no undo for this action!
	If you click a column header, the sort and filter options are displayed. For most columns, you can change the sort order (A-Z or Z-A) and/or set a filter (e.g. only display the messages of the last x hour(s)/day(s), only the ones that contain a certain string, ...). See also Filtering log messages on page 9. 
 	The applied filters are listed in the white space above the column headers. In this example, the dark blue label indicates that the messages are sorted by the values in the Type column, from A-Z (ascending). The light blue label indicates that only the messages triggered by "new flow 1" are shown.
autorefresh 	Allows you to refresh the page automatically, to always have an up-to-date overview. When turned on (default), the button is blue; when turned off, the button is gray.

Button/menu	Description
	You can enable this option only if the sort order of the "Time" column is set to "Descending (Z-A)". If you change the sort order, the autorefresh option is disabled automatically.

Columns

The following table describes the columns in the Messages overview.

Remember that you can hide columns as required via the icon in the top right corner . It's also possible to resize the columns and to move them to another position (by dragging them sideways).

The **Reset view** option sets the columns to their default position and size and makes them all visible. This option is also accessible via the context menu of the Messages view.

Column	Description
Time	Date and time when the message was triggered.
Type	Message type, indicating the severity level of the message (error, warning, info, debug or assert). See also the table below (Message types).
Module	The Switch module (such as Control) or type of flow element (such as folder) that triggered the message.
Flow	The name of the flow that triggered the message.
Element	The name of the flow element that triggered the message.
Prefix	The unique name prefix of the job referred to in the message, or blank if there is no unique name prefix.
Job	The name of the job for which this message was issued.
Message	The message itself.

Message types

The following table describes the different types of messages that can appear in the Type column of the Messages overview.

Type	Description
Info	An informational message that has no other purpose than to inform the user of a certain occurrence. <i>Info messages are always shown in the Messages overview (unless a filter is applied).</i> The Messages overview displays all types of info messages (related to Switch Server and to Switch Designer).

Type	Description
Warning	A warning message that informs the user of a recoverable problem or non-fatal error. <i>Warnings are always shown (in orange) in the Messages overview (unless a filter is applied).</i>
Error	An error message that informs the user of a fatal error. <i>Errors are always shown (in red) in the Messages overview (unless a filter is applied).</i>
Debug	An informational message solely intended for debugging purposes (often generated by configurators). <i>Debug messages are not shown by default. If the Log debug messages preference is enabled, you can display them using a filter.</i> Refer to the documentation about Switch Preferences: Logging in the Switch Reference Guide.
Assert	A message solely intended for debugging purposes that is issued only when a coding error is discovered. <i>Assert messages are not shown by default. If the Log debug messages preference is enabled, you can display them using a filter.</i> Refer to the documentation about Switch Preferences: Logging in the Switch Reference Guide.



Note: Scripters have access to all messages, to be able to debug their scripts.

2.3.2. Filtering log messages

To filter the log messages

1. Click the header of the column you want to use to filter the messages.

2. In the menu that appears, click the filter icon. 

3. Set your filter as required:

There are some small differences depending on the chosen column.


- In the **Time** column, select the filter of your choice from the list and configure it as required. For example, to only view the latest messages, select **After** and click the date and time of your choice. Other filter options are:
 - Messages issued in the last x number of hours or days
 - Messages issued before or after a particular date and time, or between two dates (with a precision of 5 minutes)

- In the **Type** column, select the checkbox of the messages type(s) you want to view in the list, for example Error and Warning. See also [The Messages overview](#) on page 6.
- In the other columns, enter one or more strings to only view the entries that contain those strings. The case of the entered strings is not taken into account.

**Note:**

- To view messages that contain several strings in one entry (e.g. configurator AND workflow), type those strings in one filter field.
- To view messages that contain either string x or string y (e.g. configurator OR workflow), type those strings in two different filter fields (see screenshot).

Extra filter fields are added by clicking  and removed by clicking the cross button. 



4. Click  to confirm.
The filter is applied immediately. The strings used to filter the messages are displayed above the columns in blue labels.
5. To clear a filter, click the cross icon in the blue label.
The label is removed and the messages overview is updated immediately.

Remark for Web Portal users only

You can save your message filters by clicking the **+ Save current filter** button in the blue navigation area.

2.3.3. Sorting log messages

To sort the log messages

1. Click the header of the column you want to use to sort the messages.
The Messages overview can be sorted by the values in all columns except for the Messages column.
2. Choose the preferred sort order:

To sort	Click
Ascending, from old to new (Time column)	
Descending, from new to old - this is the default sort order (Time column)	
Ascending, from A to Z (all other columns, except for Messages)	
Descending from Z to A (all other columns, except for Messages)	

The new sort order is applied immediately and indicated in the white space above the messages (in a blue label), e.g. "sort Module DESC" means that the messages are sorted by the items in the Module column, in descending order.

2.3.4. Exporting log messages

Log messages can be exported to a CSV file for processing by third-party tools. If you have set filters, these filters are taken into account; only the messages that are shown will be exported to a file.



Note: As of Switch 2017 it is no longer possible to export log messages to an XML file.

To export log messages

1. Open the Log messages overview.
2. Do one of the following:
 - Click the icon  in the top right corner and click **Export messages**.
 - Right-click in the overview and click **Export messages**.

A log.csv file is created.

2.3.5. Clearing log messages

Log messages are stored in a database on disk and thus remain available after quitting and restarting Switch. The application data preferences determine for how long messages are retained.

To permanently clear all log messages

1. Open the Log messages overview.
2. Do one of the following:
 - Click the icon  in the top right corner of the overview and click **Clear messages**.
 - Right-click in the overview and click **Clear messages**.


A confirmation dialog appears. If you click **Yes**, all messages will be removed from the log database. **Note that there is no undo for this action!**

2.4. Finding Switch jobs through the Switch Web Portal

2.4.1. About job boards

Job boards (aka Job finder boards) were introduced in Switch 2018. These boards provide you with a handy tool to follow up on the status of your jobs. No need to use a (Remote) Designer to watch how your jobs move through the flows; instead you can open a browser on any computer, log into the Switch Web Portal and create your own job board(s) with only those flows and jobs that are of interest to you.

Here is an example of a job board that shows you which jobs are in which stage. The jobs can be further grouped by flow or state, using the *Group by* field in the top right corner of the screen.



At the bottom of the screen, there is an extra filter 'Include jobs finished in the last x* hours', which allows you to determine how long finished jobs should remain on the job board.



Note: Access to job boards and dashboards is configured through the Users pane in Switch, hence it's possible that you don't have access to this functionality or that you can only view shared boards but not create new ones yourself.

* *Remark for Switch administrators:* Note that this value cannot be higher than the value of Keep internal job tickets for (hours) in the [Switch Application data preferences](#); if the internal job ticket

is removed, the job does not exist anymore in Switch, hence it cannot be shown anymore on a job board.

2.4.2. Creating a job board

A job board on the Switch Web Portal can display the jobs of your choice. You can select the flows for which you want to display jobs and - if you want to - only show those jobs that have a certain job status or that are in a certain job stage.



Note: Job boards are linked to your user account. Other users can't see them, unless you share them.

To create a job board

1. With the **Boards** view selected, click **+ Manage**.
If you don't see + Manage in the expanded navigation area on the left, you may not have the permissions to create boards.
The **Manage boards** dialog appears.
 2. In the bottom right corner of the dialog, click **New job board**.
If you don't see the New job board button, you may not have the permission to create boards.
 3. Configure your board:
 - a. Enter a name for your board.
 - b. Click **Select flows** (the blue button to the right of the navigation area).
 - c. In the dialog that appears, select the flows you want to see on your job board. To do so, click **Select all** (if applicable) or click the flow name of the flows you want to select.
Flow groups are shown in gray, flow names in blue. You can select all flows in a group by clicking the group name.
- 

Note: Make sure to select all flows you want to see on your job board; in the next step you can divide these flows over different columns.
- d. Click **Apply**.
 4. Configure the first column of your job board:
 - a. Enter a column name.
 - b. Select at least one flow.
 - c. Select the flow stages if applicable.
Problem jobs and **No stage** are by default available. If stages have been defined in the selected flows, they will be added and can be shown as well.
If nothing is selected, all jobs are shown, regardless of their job stage.
 5. To add another column, click the plus button  to the right of the configured column and proceed in the same way. You can add as many columns as you need.

6. Click **Save**.

2.4.3. Managing a job board

This topic explains how to handle the custom job boards on the Switch Web Portal.

Proceed as follows:

1. In the navigation area on the left, click  **Boards**.

Make sure the navigation area is expanded (by clicking ).
2. Click **+ Manage**.
The **Manage boards** dialog appears. This dialog gives an overview of the boards you have access to. The grayed out boards are shared by other users; you can view them but not make any changes. The other boards are your own boards and are fully controlled by you.
3. Do one of the following as required:

To...	Do the following:
To create a new job board	Click New job board (blue button in the bottom right corner). See also Creating a job board on page 13.
To show or hide a job board in the navigation area	Click the slider  in front of the job board you want to show or hide. If the slider is blue, the job board is visible in the sidebar.  Note: This functionality is useful for job boards you want to keep for later use or for job boards that you want to use as dataset for a dashboard (for users of the Reporting module).
To edit a job board	Click the edit button.   Note: Alternatively, you can click the edit button  beside the job board name in the navigation area. You can now edit the board name and the columns: • To change the number of flows on board level, you should click the <i>blue button</i> ("x flows selected") next to the board name. • To add a new column, click the plus icon to the right of the last configured column. 

To...	Do the following:
	To move the columns to another position, click the icon  and drag the columns you want to move sideways.  Note: Instead of dragging the sliders to make a selection, you can just click the group, flow or stage name to make a selection or to undo a selection. To return to view mode, click the Save button (in the top left corner, next to the name of the board).
To share a job board or to stop sharing it	Job boards can be shared with other members of the same user group (as configured in Switch). To share or stop sharing, in the Sharing column of the board concerned: 1. Click Private/Shared. 2. In the dialog that pops up, select or clear the checkbox of the group(s) with whom you want to share your board. If no dialog pops up, you cannot share the board (for example because you're not configured as member of a group).  Note: Shared boards can only be viewed (not edited!) by other users.
To permanently remove a job board	Click the remove button. 

4. To save the changes made in the Manage jobs dialog, click **Apply**.

2.4.4. Viewing and finding jobs on a job board

If you have the right permissions, you can view Switch jobs through the Switch Web Portal. The permissions are set by the Switch administrator through the Users pane.

To find jobs on a job board

1. In the navigation area on the left, click  **Boards**.
Make sure the navigation area is expanded (by clicking ).
2. Select one of the boards in the navigation area, below the divider.
There are two types of boards listed below the divider: job boards and dashboards (only available if the Reporting Module is licensed). The board type is mentioned in the Manage boards dialog (which can be opened by clicking **+ Manage**). Boards displayed in white are owned by you, boards displayed in blue are shared boards (which cannot be edited by you).

The selected job board is shown to the right of the navigation area. The jobs are listed in columns. What is shown depends on the configuration of the board.

3. To reorganize the overview, click the **Group by** list field in the top right corner of the screen, and select the option of your choice (**Flow**, **Stage**, **State** or **None** (which removes any previous grouping)).

A group adds an extra level to a column.

For example, suppose one of the columns of your board lists all problem jobs of all flows. With '*Group by*' set to '*None*', the jobs are put arbitrary one after the other. With '*Group by*' set to '*Flow*', the Problem jobs column is divided into different sections per flow, so you can easily see which problem job belongs to which job.

4. To search for a particular job for example to see if it reached a particular flow stage, enter (part of) the job name in the search field in the top right corner of the screen.

The search is limited to the file name (name and extension).

5. To display recently finished jobs (by default, they are not shown), enter a value in the **Include jobs finished in the last x hours** field at the bottom of the job board.

2.5. Managing dashboards on the Switch Web Portal

2.5.1. About dashboards and widgets

As of Switch 2018 update 1, it is possible to create your own dashboards on the Switch Portal. This requires a license for the Reporting Module.

Dashboards on the Switch Web Portal can give you a quick overview of the *number of jobs* that are being processed by the Switch Server. You can for example display a counter (how many jobs failed, how many jobs are in a particular stage,...) or a graph with numbers per file type, flow,... It's also possible to visualize historical job data (e.g. number of problem jobs per week over the past 3 months).

The graphs and counters are actually **widgets** that can be configured at wish. The input for these widgets (i.e. the data that is visualized) comes from a job board. The widgets can be customized to a certain level: you can for example add a frame around a widget in the color of your choice, you can add a title, in case of a graph you have the choice between a bar, a donut or a pie chart,...

Currently, six different widgets are available for use on the Switch Web Portal. They are listed below.




Note: Access to job boards and dashboards is configured through the Users pane in Switch, hence it's possible that you don't have access to this functionality or that you can only view shared boards but not create new ones yourself.


Column Layout

This is actually a layout that helps you position the widgets on the screen. You need it to put different widgets next to each other. If you want to put the widgets one after the other, in a vertical arrangement, you don't need a layout.

Example of 2 live counters in a column layout (horizontal arrangement):



Example of 2 live counters without column layout (vertical arrangement):



See also: [Dashboard widgets - Column Layout](#) on page 23

Custom HTML

This widget allows you to add a title, a logo, text and even a movie to your dashboard.



See also: [Dashboard widgets - Custom HTML](#) on page 24

Live counter


This widget displays a number, representing the amount of jobs currently present on the selected job board.



See also: [Dashboard widgets - Live counter](#) on page 24

Live graph

This widget counts both the total number of the jobs on the selected job board and the number of jobs per column, and presents this data as a graph.



See also: [Dashboard widgets - Live graph](#) on page 25

Live table


This widget displays **information about the jobs** counted in a live graph on the same dashboard. For example, if your graph gives an overview of the number of jobs per flow, the live table displays detailed information about these jobs (job name, flow name, stage and state of the job).

Details				
Set	Name	Flow	Stage	State
filter column...	filter column...	filter c	filter column...	filter column
Jobs in production	20pp.ppp	FlowB	Problem jobs	Input
Jobs in production	switch_quickstar	FlowC	Problem jobs	Production
Jobs in production	switch_quickstar	FlowC	Problem jobs	Production
Jobs in production	masked text 2.pc	FlowC	Problem jobs	Production
Jobs in production	masked text 2.pc	FlowC	Problem jobs	Production
Jobs in production	Enfocus_PriceLis	FlowC	Problem jobs	Production
Jobs in production	[Content_Types].	FlowC	Problem jobs	Production
Jobs in production	Enfocus_PriceLis	FlowC	Problem jobs	Production

See also: [Dashboard widgets - Live table](#) on page 27

History graph

This widget visualizes the evolution of the number of jobs or the job size over a particular period of time, for example the total number of problem jobs of the last month, grouped by week.



See also: [Dashboard widgets - History graph](#) on page 27

2.5.2. Creating a dashboard

A dashboard is an overview screen with one or more widgets that visualize job data.

Before you start, make sure to [create a job board](#) with the data you want to display on the dashboard. Alternatively, you may use a shared job board. A job board to start from is necessary

for all widgets, except for the history graphs and custom HTML. For example, if you want your dashboard to display the total number of problem jobs on the server, you need a job board that collects all problem jobs.



Note: Job boards are linked to your user account. Other users can't see them, unless you share them.

To create a dashboard

1. With the **Boards** view selected, click **+ Manage**.
If you don't see + Manage, you may not have the permission to create boards.
The **Manage boards** dialog appears.
2. In the bottom right corner of the dialog, click **New dashboard**.
If you don't see the New dashboard button, you may not have the permission to create boards.
3. Configure your board:
 - a. Enter a name for your board.
 - b. Choose a layout:
 - If you want to place the different widgets one below the other (**vertical arrangement**), you don't need a layout. If there is one on your dashboard (default configuration when creating a new board), click the remove button  to remove it.
 - If you want a **horizontal arrangement with two or more columns** next to each other, you need a column layout. If there is one on your dashboard (default configuration when creating a new board), click the edit button  to configure it. Refer to [Dashboard widgets - Column Layout](#) on page 23.
 - c. Drag and drop one or more widgets onto the column of your choice (in case of a column layout) or directly onto the dashboard and configure them as required:
 - [Dashboard widgets - Custom HTML](#) on page 24
 - [Dashboard widgets - Live counter](#) on page 24
 - [Dashboard widgets - Live graph](#) on page 25
 - [Dashboard widgets - Live table](#) on page 27
 - [Dashboard widgets - History graph](#) on page 27
 - d. To switch between configuration or edit mode and view mode:
 - Click the edit button  in the header of the widget to make changes.
 - Click the view button  in the header of the widget to view the result of your changes.
4. Click **Save**.
The dashboard is added to the navigation area.

Note that you can still make changes by clicking the edit button  beside the name of the dashboard in the navigation area.

2.5.3. Managing a dashboard

This topic explains how to handle the custom dashboards on the Switch Web Portal.

Remember that dashboards are only available if the Reporting Module is licensed.

Proceed as follows:

1. In the navigation area on the left, click  **Boards**.

Make sure the navigation area is expanded (by clicking ).
2. Click **+ Manage**.
The **Manage boards** dialog appears. This dialog gives an overview of the boards you have access to. The grayed out boards are shared by other users; you can view them but not make any changes. The other boards are your own boards and are fully controlled by you.
3. Do one of the following as required:

To...	Do the following:
To create a new dashboard	Click New dashboard (blue button in the bottom right corner). See also Creating a dashboard on page 19.
To show or hide a dashboard in the navigation area	Click the slider  in front of the dashboard you want to show or hide. If the slider is blue, the dashboard is visible in the sidebar.  Note: This functionality is useful for dashboards you want to keep for later use.
To edit a dashboard	Click the edit button.   Note: Alternatively, you can click the edit button  beside the dashboard name in the navigation area. You can now add or remove widgets and make changes to the widgets as required: • To add a widget, click it (in the right part of the screen) and drag it onto the dashboard. • To remove a widget, click the remove button  in the header of the widget. • To make changes to a widget, click the edit button  in the header of the widget.

To...	Do the following:
	To view your changes, click the view button  in the header of the widget. Do not forget to save your changes, by clicking the Save button (in the top left corner, next to the name of the dashboard). By saving your changes, you automatically switch to view mode.
To share a dashboard or to stop sharing it	Dashboards can be shared with other members of the same user group (as configured in Switch). To share or stop sharing, in the Sharing column of the board concerned: - Click Private/Shared. - In the dialog that pops up, select or clear the checkbox of the group(s) with whom you want to share your board. If no dialog pops up, you cannot share the board (for example because you're not configured as member of a group).  Note: Shared boards can only be viewed (not edited!) by other users.
To permanently remove a dashboard	Click the remove button. 

4. To save the changes made in the Manage jobs dialog, click **Apply**.

2.5.4. Viewing a dashboard

If you have the right permissions, you can create and view dashboards through the Switch Web Portal. The permissions are set by the Switch administrator through the Users pane.

To view your (earlier created or shared) dashboards on the Switch Web Portal

- In the navigation area on the left, click  **Boards**.
Make sure the navigation area is expanded (by clicking ).
- Click one of the boards in the navigation area, below the divider.
There are two types of boards listed below the divider: job boards and dashboards (only available if the Reporting Module is licensed). The board type is mentioned in the Manage boards dialog (which can be opened by clicking **+ Manage**). Boards displayed in white are your own boards, boards displayed in blue are shared boards (which cannot be edited by you).
The dashboard is shown to the right of the navigation area. There may be several widgets present on the dashboard. Some of the widgets show extra information when hovering or

clicking the legend. For more information, refer to the description of the widgets ([Dashboard widgets overview](#) on page 23).

2.5.5. Dashboard widgets overview

This is an overview of the widgets available for use on a Dashboard on the Switch Web Portal.

2.5.5.1. Dashboard widgets - Column Layout

About the Column Layout

The column layout is actually a layout, so not a graph or a counter. It allows you to place several widgets next to each other in columns, for a horizontal arrangement. If no column layout is chosen, the widgets will be placed one after the other, in a vertical arrangement.

How to configure the Column Layout

By default, two columns are available, but you can add more columns by switching to edit mode  and clicking the  button.

Note that you should first *configure* the column layout; afterwards (after having saved/having clicked the  button) you can drag the widgets onto the layout.

Properties

Property	Description
Spacing	White space between two columns. You can enter a value expressed in the unit of your choice: px, em or % When using pixels or em, the size of the white space will be fixed; when using a percentage, the white space will adjust when the screen is resized. Note that this setting is optional and only needed when you want separate the widgets.
Columns with width settings	For each of the individual columns you can either define a column width or a minimum and/or maximum width. The width can be fixed (expressed in px or %) or "fit the content" (meaning that you let Switch decide which is the best size).
Show frame	When selected, a thin frame is drawn around the widget and the following additional properties are displayed:
Title	Text that will be shown in the title bar of the widget. You can leave it empty as required.

Property	Description
<i>Frame color</i>	Color that will be used for the title bar and the frame around the widget. Clicking the color patch will open a color picker dialog.

2.5.5.2. Dashboard widgets - Custom HTML

About the Custom HTML widget

This widget allows you to add text, tables, pictures, movies and links to your dashboard. You can use the text color and font of your choice, insert bullets, ...

How to configure the Custom HTML widget

You can type text in the text field and modify it using the tools in the editor.

An overview of shortcuts is available behind the question mark button. 

Properties

Property	Description
Show frame	When selected, a thin frame is drawn around the widget and the following additional properties are displayed:
<i>Title</i>	Text that will be shown in the title bar of the widget. You can leave it empty as required.
<i>Frame color</i>	Color that will be used for the title bar and the frame around the widget. Clicking the color patch will open a color picker dialog.

2.5.5.3. Dashboard widgets - Live counter

About the Live counter widget

This widget displays a number, representing the amount of jobs currently present on the selected job board. Note that all jobs in all columns are taken together, resulting in one number, for example the number of problem jobs.

This number can be linked with a color, for example, if the number of jobs remains below a certain threshold, the background of the widget turns green; otherwise it turns orange or red.

The counter is updated at regular intervals (see properties), giving a live view on the Switch server.

How to configure the Live counter widget

You can configure the properties listed in the table below.

Properties

Property	Description
Job board	Data that will be used for the dashboard.

Property	Description
	'None' is not a valid option.
Include jobs finished in the last (hours)	The value chosen here determines how long after finishing the jobs will be included in the live counter. If you enter '0', only jobs that are still moving through the flow and haven't reached an output folder will be included. If the widget doesn't behave as expected, contact your Switch administrator. There may be a conflict with the Keep internal job tickets for (hours) in the Switch Application data preferences.
Color	Background color of the widget based on the value of the counter. To change a value, click it and increase or decrease the value using the small arrow buttons. To change a color, click it to open the color picker and select the color of your choice. Note that there's also a small text field below the color patches. You can click it and type the text of your choice. This text will be displayed below the counter.
Refresh interval (in seconds)	This value indicates how often the number of jobs is recalculated.
Show frame	When selected, a thin frame is drawn around the widget and the following additional properties are displayed:
<i>Title</i>	Text that will be shown in the title bar of the widget. You can leave it empty as required.
<i>Frame color</i>	Color that will be used for the title bar and the frame around the widget. Clicking the color patch will open a color picker dialog.

2.5.5.4. Dashboard widgets - Live graph

About the Live graph widget

This widget counts both the total number of the jobs on the selected job board and the number of jobs per column, and presents this info in a graph.

Note that this requires a job board with more than one column; each column is represented as a separate section in the graph. You can choose between a pie, a bar and a donut chart.

How to configure the Live graph widget

You can configure the properties listed in the table below.

Properties

Property	Description
Chart	Type of chart to be used. Options are: • Pie

Property	Description
	• Donut • Bar  Tip: Use "Pie" and "Donut" to show how the parts (i.e. values per column) compare to the whole (total number of jobs); use "Bar" to show how the parts compare to each other or to show trends.
Show grid lines	If selected, grid lines are shown to make it easier to read the values.  Note: This option is not relevant (hence not available) for pie and donut charts.
Job board	Data that will be used for the dashboard. For this type of charts, you should have a board with more than one column. 'None' is not a valid option.
Include jobs finished in the last (hours)	The value chosen here determines how long after finishing the jobs will be included in the live graph. If you enter '0', only jobs that are still moving through the flow and haven't reached an output folder will be included. If the widget doesn't behave as expected, contact your Switch administrator. There maybe a conflict with the Keep internal job tickets for (hours) in the Switch Application data preferences.
Refresh interval (in seconds)	This value indicates how often the values are recalculated.
Show frame	When selected, a thin frame is drawn around the widget and the following additional properties are displayed:
<i>Title</i>	Text that will be shown in the title bar of the widget. You can leave it empty as required.
<i>Frame color</i>	Color that will be used for the title bar and the frame around the widget. Clicking the color patch will open a color picker dialog.

How to use Live graphs

Smaller parts are not always easy to read, so when **hovering over one particular part of the chart**, this part is highlighted and you get a small dialog with the column name and the percentage value of the highlighted part.

When **clicking an item in the legend**, the corresponding part of the chart is disabled (grayed out in the legend) and taken out of the chart. Clicking once more will bring it back.

2.5.5.5. Dashboard widgets - Live table

About the Live table widget

This widget displays **information about the jobs** counted in a live graph on the same dashboard. For example, if your graph gives an overview of the number of jobs per flow, the live table displays detailed information about these jobs (job name, flow name, stage and state of the job).

How to configure the Live table widget

You can configure the properties listed in the table below.

Properties

Property	Description
Parent	Live graph that is used as dataset for the live table. 'None' is not a valid option.
Show frame	When selected, a thin frame is drawn around the widget and the following additional properties are displayed:
Title	Text that will be shown in the title bar of the widget. You can leave it empty as required.
Frame color	Color that will be used for the title bar and the frame around the widget. Clicking the color patch will open a color picker dialog.

How to use live tables

To **see the details of a particular part/category in the chart**, e.g. one slice of the pie, just click in the chart. Only the details of the corresponding jobs will be shown in the table. Clicking once more will reset the table.

To **search for a particular job/a set of jobs**, you can filter the table by entering a key word in the filter fields below the column headers. Note that these filter fields are not case sensitive.

To **sort the list in ascending or descending order**, click the column header of the column by which you want to order it. Note that the small arrow in the column header will become a bit darker, to indicate this.

2.5.5.6. Dashboard widgets - History graph

About the History graph widget

A history graph **visualizes the evolution of the number of jobs or the job size over a particular period of time**, for example the total number of problem jobs of the last month, grouped by week. A further subdivision is possible, you can for example further group the jobs by file type, flow, stage or state.

Note that this graph only counts jobs that are completely finished, meaning that they have left the Switch flows. Data is available for the time period set in the user preferences, for example for 120 days. Refer to the Switch Reference Guide (Switch Preferences: Dashboard)

How to configure the History graph widget

You can configure the properties listed in the table below.

Properties

Property	Description
Chart	Type of chart to be used. Options are: • Line • Spline (curved line) • Bar • Pie
Show grid lines	If selected, grid lines are shown to make it easier to read the values.  Note: This option is not relevant (hence not available) for pie charts.
Job board (single column only)	For the time being, only job boards with one column are supported. 'None' is a valid option for history graphs: if selected, all jobs on the Switch server are taken into account!
Unit	Determines what is counted and displayed: • Number of jobs • Total size
Group by	Determines how the values are grouped: • None: no grouping; the total number of jobs or the total size is mentioned. For example, 200 jobs on day1, 190 jobs on day 2, etc. • Type: the total number or the total size is further divided by file type. For example, 100 PDF files and 100 text files on day1, 90 PDF files and 100 text files on day2, ... • Stage: the total number or the total size is further divided by flow stage. For example, 75 jobs in stage1 and 125 in stage2 on day1, 70 in stage1 and 120 in stage2 on day2, ...  Note: Stages that were not selected on the job board are not shown. • State: the total number or the total size is further divided by job state. For example, 33 jobs in state1 and 167 in state2 on day1, 22 in state1 and 168 in state2 on day2, ... • Flow: the total number or the total size is further divided by flow. For example, 50 jobs in flow1, 50 in flow2 and 100 in flow3 on day1, 99 in flow, 1 in flow2 and 90 in flow3 on day2, ...  Note: Flows that were not selected on the job board are not shown.

Property	Description
	• Element: the total number or the total size is further divided by flow element. For example, 2 jobs have been put in the recycle bin, 7 jobs have been processed by the Enfocus PitStop Server configurator, ... Note that all elements in all flows are taken together, regardless of the name of the instance in the flows. For example, even if the recycle bins in your flows are called 'Trash1', 'Trash2', 'Trash3', in the graph you'll see 1 flow element 'recycle bin' (with all jobs collected in all 3 trash folders). As for the folder element: only input folders are taken into account. Intermediate and output folders nor problem folders are represented in the graph.
Period	Determines how the data will be grouped, i.e. which data will be taken together. • Day • Week • Month For example, if grouped by week, you'll get one value for all jobs of a particular week (optionally further divided by flow, file type, etc.)  Note: This field is not available if the 'Pie' chart is chosen.
Days previously	Refers to the time period that will be shown in the graph. For example, if set to '200', the data of the last 200 days (= today minus 200 days) will be shown. Note that the maximum number of days that is possible is determined by the Reporting preference (see higher).
Show frame	When selected, a thin frame is drawn around the widget and the following additional properties are displayed:
Title	Text that will be shown in the title bar of the widget. You can leave it empty as required.
Frame color	Color that will be used for the title bar and the frame around the widget. Clicking the color patch will open a color picker dialog.

How to use history graphs

Smaller parts are not always easy to read, so when **hovering over one particular part of the chart**, this part is highlighted and you get a small dialog with more information (for example the number of jobs/the total size per group; if there is no grouping, the dialog mentions the "overall" value).

When **clicking an item in the legend**, the corresponding part of the chart is disabled (grayed out in the legend) and taken out of the chart. Clicking once more will bring it back.

2.6. Submitting and checking jobs through the Switch Web Portal

Submitting and checking jobs through the Switch Web Portal is only possible if you have licensed the **SwitchClient Module (2017 or higher)** and you're using the new, **web-based version** of the client. In that case, the *job client type* option (in the Internal Communications preferences) must be set to *Default*.

Overview

An active SwitchClient Module gives access to the following functionality:

- Connect to one or more Switch Servers on the local network/internet.
- Submit jobs (files or job folders) and metadata describing these jobs to a Submit point in a flow.
- Review and act on jobs being held in a Checkpoint in a flow.
- View progress information and the status of submitted jobs.
- View log messages issued by processes on the server.

Good to know

- Access to particular Submit points and Checkpoints can be restricted, by configuring access rights at user or user group level.
- Metadata information attached to a job can be used to make automated routing decisions or to provide variable input to various tools and configurators.
- If you want to connect to more than one Switch Server at a time, you must open a browser window per server and sign in to the Switch Web Portal for each server separately. The IP address of the server is displayed in the URL.

2.6.1. Setup in Switch

Allowing users to submit and check jobs via the Switch Web Portal, requires **some preparation in Switch**, usually done by a system administrator.

This includes:

- Installing and activating Switch (this includes activating the SwitchClient Module)
- Designing and activating one or more flows that will process the jobs submitted and monitored through the Switch Web Portal.
- Configuring user access rights (in the Users pane)

- Configuring or checking the communication settings (through the Switch user Preferences)

2.6.1.1. Installing and activating Switch and the SwitchClient Module

Licenses

A regular SwitchClient Module includes a license for **up to five concurrent connections**. If this is not sufficient, you can purchase additional licenses. The number of licenses can be raised by entering a new activation key in the **Manage licenses** dialog in Switch.

An active SwitchClient Module allows you access to the following flow elements:

- Submit point
- Checkpoint
- Checkpoint via mail

If SwitchClient is not licensed, the above flow elements will not be available and you will not be able to submit and check jobs through the Switch Web Portal.

Remark: To avoid misuse, we allow 200 submits per licensed client connection per hour. For most customers this will be enough. If this is not the case (e.g. you get the following warning: "You reached the maximum number of calls"), please consider buying additional SwitchClient licenses or a Web Services license (unlimited number of users).

How to proceed

Follow the guidelines and instructions described in the Switch Reference Guide ("Installing, activating and starting Switch"):

1. Install Switch.
2. Activate Switch, including the SwitchClient Module.
3. Activate additional licenses if required.

2.6.1.2. Designing flows for use with the Switch Web Portal

Managing files through the Switch Web Portal requires a particular flow design in Switch.

About flows in Switch

To design a flow, the Switch user drags flow elements (such as Submit points, processors and folders) on the canvas and connects them according to the desired job flow. After configuring appropriate property values for each flow element (and in some cases, the connections), the Switch user can activate the flow for execution. From then on, Switch automatically moves and processes jobs along the flow.

If you're new to Switch, we recommend having a look at the Switch Quick Start Guide (available on the [Enfocus website](#)).

Dedicated flow elements


Submit points and **Checkpoints** are flow elements designed for use with the Switch Web Portal. For more information, refer to the Switch Reference Guide (Flow elements: overview > Communication).

**Note:**

- Make sure the **flows you want to use with the Switch Web Portal are active**. A user with the appropriate access rights can access Submit points, Checkpoints and jobs in inactive flows but the jobs will not move along the flow.
- **The Switch Web Portal only interacts with the Switch Server**, not with the Switch Designer. Users can safely quit the Designer without disturbing the operations via the Portal as long as the Switch Server is running. For more info on the behavior of Switch when exiting the flow designer, refer to the Switch user preferences (User interface).

Example flow

Here's a flow example as it is shown on the Switch canvas:



Since this example focuses on Web Portal features, there is a lot of interaction with human operators and little automated processing (other than moving jobs around). Real-life flows would probably include processing steps such as preflight or color conversion.

The **Submit point on the left** (*Creatives*) allows submitting jobs to the flow in a controlled way using the Switch Web Portal. The user's name is automatically remembered; multiple users can use the same Submit point since each user is identified to Switch through his/her user name and password. The "Set User Name" script serves to add a user name for jobs submitted through a regular hot folder (Henry).

The **first Checkpoint** (*Visual Proof*) holds the incoming jobs for inspection by a user through the Switch Web Portal. The user will see the names of the output connections (Approve and Decline) as buttons in the job card. Pressing one of these buttons moves a job along the corresponding connection.

The **second Checkpoint** (*Output Jobs*) allows a Switch Web Portal user to decide how the jobs will be stored or processed. This Checkpoint is configured to allow multiple outputs at the same time; for example both "Store in DAM" and "Create Proof".

Setting up a Submit point

When setting up a Submit point (*Creatives* in the example flow), you can configure it in such a way that the user must enter one or more data fields before submitting a job to this Submit point. The entered values are associated with the job as metadata.

To enable this option, in the properties of the Submit point element:

1. Set **Enter metadata** to **Yes**.
2. Double-click the **Metadata fields** property and define the metadata fields for which the user should provide a value, for example a Job ID and the date of submission.
3. The **Dataset name** field is completed automatically. This is the name of the dataset that will be created containing the contents of the metadata fields entered by the user.

For a full description, refer to "Defining metadata fields" in the Switch Reference Guide.

The following screenshot shows how a user will have to enter the data (Job ID and Date) configured in the Submit point.

The screenshot displays a form titled "AdCampaign.pdf" with a blue header. Below the header, it shows the flow "SwitchClient - Flow 1" and the submit point "Creatives". The form contains two input fields: "Job ID" and "Date". The "Date" field is pre-filled with "2017-01-30" and includes a calendar icon. At the bottom, there is a "Job name" field with the value "AdCampaign", and two buttons: "Cancel" and "Submit".

Setting up a Checkpoint

Similarly, when setting up a Checkpoint (*Visual Proof* and *Output Jobs* in the example flow), you can ask Switch to display additional information about the job, and the user may be asked to

enter additional data fields before acknowledging a job. (This is the case if the **Enter and display metadata** property is set).

Furthermore, the **output connections of the Checkpoint determine which buttons will be shown** to the user for acknowledging a job.

For example, the *Visual Proof* Checkpoint in the example flow is configured in such a way that the user will see two radio buttons ('Decline' and 'Approve', named after the connections); clicking one of the buttons causes the job to move along the corresponding connection. This is the default behavior of a Checkpoint if two output connections are defined and no metadata has been enabled.



On the other hand, the *Output Jobs* Checkpoint in the example flow is configured in such a way that the user can select **more than one option**, causing a duplicate of the job to be sent out over each of those connections. This is possible if the **Allow multiple outputs** property is enabled.

In this example, the user that has to review the files will see 3 checkboxes (the names come from the output connections in Switch) and can select one, two, or three checkboxes as required.



For an overview of all properties, refer to the description of the Checkpoint flow element in the Switch Reference Guide.

Metadata in Submit points and Checkpoints - default values

When defining the default values for the metadata fields, you can use a number of variables that automatically retrieve information from the computer that is used to submit or check jobs. As a consequence, this information does not need to be entered explicitly by the user; it can even be sent along with the job without being displayed.

The variables concerned are the so-called Connection variables:

- [Connection.Email]
- [Connection.FullUserName]
- [Connection.IP]
- [Connection.UserName]

If you use those as default values for your metadata fields, they will be replaced automatically with their actual values.

To make this happen, "bidirectional communication" is established between Switch and the Switch Web Portal:

1. The Switch Web Portal requests the default value of the metadata fields, being a connection variable.
2. Switch Server sends the connection variable e.g. [Connection.IP] to the Portal.


3. The Portal replaces the variable with its actual value and sends the actual value along with the job back to Switch Server.

Use case: To keep track of the clients used to submit jobs, you could configure a metadata field "IP address" and set the default to [Connection.IP]. When a file is submitted, the IP address of the system used to submit this file is entered automatically and sent along with the job. It depends on the metadata field properties whether or not this field (with the actual value) is shown to the user and whether or not it can be changed.

Re-using metadata fields from a Submit point in a Checkpoint

Switch provides an easy way to re-use the metadata fields defined for Submit points in a particular Checkpoint.

To re-use an existing metadata field, simply click the  button (instead of the green plus button) in the Define metadata fields dialog. This will open a dialog like the one shown below.




You can now select the metadata fields you want to re-use (based on the Submit points defined for the current flow). Note that the added metadata fields have only two editable options: **Read only** (yes/no) and **Display metadata field** (yes/no). The other options are grayed out and cannot be changed.

Remark: Although all Submit points present in the flow are shown, you must keep in mind that only the Submit point that is used for the job will send metadata. Refer to the example below:

since all jobs in Checkpoint 1 come from Submit point 1, it does not make sense to add metadata from Submit point 2 to Checkpoint 1 (and vice versa).

If configured incorrectly, the connection variables (if used) will not be replaced with the actual values (users will see e.g. [Connection.UserName]) and metadata fields for which there is no value entered will be blank.

If configured correctly, when checking the Alert job on the Portal, the connection variables (if used) will be replaced with the actual values (e.g. EAW13DL399 instead of the [Connection.IP]) and the metadata fields that were completed at the time of submission will show the entered data.



2.6.1.3. Configuring user access

How to proceed

Follow the guidelines and instructions described in the Switch Reference Guide ('Configuring users'):

1. Set up the appropriate users and configure their user name, password, email address,...
2. Give them access to the appropriate Submit points and Checkpoints.

2.6.1.4. Configuring the communication settings

To configure the communication settings for communication with the Switch Web Portal

1. Navigate to:
 - On Windows: **Edit > Preferences.**
 - On Mac OS: **Enfocus Switch > Preferences.**

The User preferences dialog appears.

2. In the left part of the dialog, click **Internal communication.**
3. Make sure that **Job client type** is set to **Default.**

This indicates that you're using the new web-based client instead of the old SwitchClient desktop application.


4. In the left part of the dialog, click the **Web services** category.

5. Make sure the **Port for the Switch Web Portal** preference is set to 51089, unless there is a good reason to change it.
6. Click **OK**.

2.6.2. The Switch Web Portal User Interface

2.6.2.1. The navigation area

When opening the Switch Web Portal, you can access the functionality to submit and check jobs through the navigation area in the left part of the screen. This area can be collapsed or expanded; when collapsed (see screenshot), the icons remain visible allowing you to switch to the appropriate view. The view that is active is highlighted; in this example, that is the Submit jobs view.



The table below explains the meaning of the buttons in the navigation area.

Button	Click this button to...
	Expand or collapse the menu.
	Display the Submit jobs view.
	Display the Check jobs view.
	Find more info. A new dialog is opened with links to: - The Switch documentation on the website - The Enfocis Support Portal (to report a problem)


Button	Click this button to...
	- The Support page on the Enfocus website - The Switch system requirements.




Note: Depending on your permissions, you may see two extra buttons in the navigation area, giving access to the log messages  and the boards . For more information, refer to [Finding Switch jobs through the Switch Web Portal](#) on page 12, [Managing dashboards on the Switch Web Portal](#) on page 16 and [Viewing log messages through the Switch Web Portal](#) on page 5.

2.6.2.2. Submit jobs view

The Submit jobs view allows you to submit Jobs to the Switch Server. You can see all Submit points that you have access to, based on your permissions (as set in the Users pane in Switch).



When you hover over a Submit point, it changes as shown on the screenshot:



The upper area is the 'drag and drop' area; the lower area consist of two buttons, which allow you to browse to the files you need. The first button should be used to submit *files*, the second one to submit *folders*.


Once you have submitted a job, you will see one of the following icons at the bottom of the screen:

Icon	Meaning
	Indicates that a job is being uploaded. You can click it to see the percentage of completion.
	Indicates that the jobs that were submitted in the current session were uploaded successfully. You can click the icon to see which jobs were uploaded.

2.6.2.3. Check jobs view

This view allows you to view jobs submitted through a Submit point on the Switch Web Portal, and to check and route jobs waiting in a Checkpoint.

It depends on your user permissions (set in the Users pane in Switch) which jobs you can see and/or further process.



This view has a couple of extra buttons:


Button	Meaning
	Click this button to manage the filters that allow you to only display a <i>subset</i> of the jobs that you have access to. When you click this button, the navigation area expands automatically, so you can see the pre-configured filters (My jobs, Alert jobs, Active jobs, Completed jobs) and the ones you have created yourself (see screenshot below).
	The label in the upper part of the overview refers to the <i>custom</i> filter that is currently applied. If you want to stop filtering based upon that filter, you can click the cross icon. Note that <i>pre-configured</i> filters are not marked by a label when they are applied. You can see that they are applied, when they are highlighted in the navigation area.
	This button allows you to change the sort order of the jobs in the overview. In this example, the jobs are sorted in descending order (arrow down) by the date they were last updated (= value of the field "Updated").
 	This button allows you to Switch between table view and grid view (as on the screenshot): In table view, every row represents a job; the job details are shown in the different columns.

Button	Meaning
	In grid view, every job card represents a job; the job details are listed on this card.

Filters

This is an example of how the navigation area looks when expanded.

The filter that is applied ("Filter Drupa files" in this example) is highlighted.



Note the counter next to 'Check jobs'. It indicates the number of "alert" jobs waiting to be processed.

2.6.3. Submitting jobs through the Switch Web Portal

It is possible to submit single files or multiple files, or files contained in a folder (for example a page layout with its accompanying images and fonts or the individual pages in a book). A job folder may contain nested subfolders (which can contain other files and folders, recursively).


If the files are contained in a folder, they will be considered as one job with one dataset; it will not be possible to enter metadata for each file separately.



Note: Remember that the Switch Server must be running and that the Switch flow must be activated. Otherwise, the jobs will not be processed.

To submit a job to a particular Submit point:

1. In the Switch Web Portal, in the navigation area, click  **Submit jobs**. You can see the Submit points you have access to.
2. Do one of the following:
 - "Drag and drop" the file(s) or folder(s) you want to submit onto the Submit point of your choice. Make sure the files are dropped on the upper part (drag & drop area).
 - Hover over the Submit point of your choice, and click the appropriate button in the lower part. The first button is to be used for files, the second for folders. You can then browse to the files or folders you need and select them.




To select multiple files or folder, hold down the **Ctrl** key while selecting.

3. *If you have selected several files*, you must first decide if you want to process them as **separate jobs** or as **one job**. Click the button of your choice.
If you choose to process them as one job, the files will be submitted to and moved along the flow as a single entity.
4. *If the Submit point has been configured to request additional information about the job* ("metadata"), you'll get a dialog with one or more entry fields. Enter the requested information.
5. Change the job name as required.
The chosen job name will replace the file name. For example, if the job name is "testjob", the job file "customerX.pdf " will be renamed "testjob.pdf". The file extension remains the same.

In case of a job folder, the job name will replace the name of the folder. The files contained in this folder will not be renamed.

In case of multiple files being submitted in one go, you cannot enter a job name, unless you have chosen to process them as one job; in that case, they are put in a folder and the chosen job name will be the folder name.
6. Click **Submit**.

Note that there is a progress indicator at the bottom of the screen. If you click the icon, you can see which files have been submitted successfully, and/or which are still uploading.



2.6.4. Viewing jobs through the Switch Web Portal

To view Switch jobs through the Switch Web Portal

1. In the Switch Web Portal, in the navigation area, click  **Check jobs**.
You can see all jobs you are allowed to see based on your user permissions (set in the Switch Users pane). The counter (only shown if the menu is expanded) indicates the number of files waiting in a Checkpoint.
2. To view only a particular set of jobs, apply a filter.

Make sure the navigation area is expanded (by clicking  or ).



- Click one of the pre-configured filters in the navigation area below **Check jobs**, for example 'My jobs'. Refer to [Job filters](#) on page 45.
- Create a filter yourself. Refer to [Creating a custom filter](#) on page 46.

The jobs matching the selected filter (now highlighted in the navigation area) are shown. If you don't see the jobs you expected to see, check if:

- The Switch Server is running.
- The information displayed is up-to-date. Refresh your browser window to update the information from the Switch Server.

Note that you can stop filtering by clicking the filter name in the navigation area once more. Alternatively, in case of a custom filter, you can create the cross icon in the *label* (shown in the upper part of the overview).

3. To view the jobs presented in a different way, click the table view or the grid view button at the bottom of the screen.

View	Example
Table	 Table-specific options: - To hide a column, click the icon  in the top right corner and clear the checkbox of the column you want to hide. Note that you can go back to the default view (and column size/position) via the Refresh columns option at the bottom of this list. - To move the columns, drag them sideways. - To sort the overview, click the header of the column you want to use to sort the overview and click the order of your choice (A-Z or Z-A).
Grid view	

4. To view the details of a job and eventually review and process the job:
- In table view, click the row concerned.
 - In grid view, click the **Process** button of the job you want to check and/or process.

See also: [Reviewing and processing jobs through the Switch Web Portal](#) on page 48.

2.6.4.1. Job statuses

The following table gives an overview of the statuses a job can have on the Switch Web Portal.

Status	Meaning
Processing	The job resides somewhere in the flow but not in a Checkpoint, and it is not finished yet. This includes jobs in the Problem jobs flow element.
Alert	The job resides in a Checkpoint and is waiting for intervention by an operator. The number of alert jobs is indicated by a counter in the navigation area of the Web Portal.
Error	The job failed. You should contact your system administrator for more information.
Completed	The job has been processed and has arrived in the output folder of the flow.

2.6.4.2. Job filters

Default job filters

The table below provides an overview of the default, pre-configured filters in the Check jobs view on the Switch Web Portal.

Filter	Displays:
My Jobs	All jobs submitted by you, i.e. the current user, regardless of their current status (processing, alert, completed).
Alert Jobs	All jobs waiting in a Checkpoint.  Note: You can only see the jobs in a Checkpoint that you are allowed to access (as configured in the Users pane in Switch).
Active Jobs	All jobs that are somewhere in the flow, but not in an end folder (that is, not yet completed). This includes files that reside in the Problem jobs folder.  Note: This only applies to jobs that are visible to you.
Completed Jobs	Displays all the jobs that reside in an end folder in Switch.  Note: This only applies to jobs that are visible to you.

Custom job filters

You can as well create your own filters, for example you can create a filter to display all jobs in a particular Submit point or Checkpoint, all jobs with a particular status, all jobs initiated before or after a particular time, etc.

Refer to [Creating a custom filter](#) on page 46.

Note that these filters are not visible to other Switch users signing in to the Switch Web Portal.

No filter applied

If no filter is applied, you can see all jobs you are allowed to manage.

2.6.4.3. Creating a custom filter

In the Check jobs view on the Switch Web Portal, you can create your own, custom filters.

You could for example create a filter that displays all jobs with a certain status that were submitted to a particular Submit point.

To create a custom filter

1. Do one of the following:
 - In the navigation area, click **+ Create filter**.
 - Click in the upper part of the screen on "Create filter".
2. In the dialog that pops up, beside the **Close** button, enter a meaningful name for the custom filter.
Each filter needs to have a unique name.
3. Configure a filter rule: select the appropriate filter field, choose an operator and enter the value of your choice.

Example filter fields are: Checkpoint, On alert since, Files, Flow, ... "Familystarter" refers to the first job in a job family, being a set of jobs that have been generated from the same original job. For example, a PDF, its Preflight Report, the preflighted and the low res version, ... they all belong to the same job family.

4. To configure a second rule or rule set, click the appropriate button:
 - To add one rule, click the green **Add rule** button.
 - To add several rules, which are related to each other (through an AND/OR relation), click the green **Add group** button.

If you have made a mistake, you can remove the rule concerned by clicking the red **Delete** button.

5. Once you have configured your rules, make sure to indicate the relation between the rules and the rule groups, by clicking the appropriate button:
 - **And** means that for each job it is checked if all rules apply. For example, with *Checkpoint = Checkpoint 1 AND job status = alert* only the jobs in Checkpoint 1 that have the alert status will be shown.
 - **Or** means that at least one of the rules should apply. For example, with *Checkpoint = Checkpoint 1 OR job status = alert*, all jobs in Checkpoint 1 are shown (regardless of their status) and all jobs that have the alert status (regardless of the Checkpoint they are in).

The And/Or option is only relevant if you're configuring more than one rule.

The following example results in a list of jobs submitted to Submit point 1 AND having a certain status, which can be either Alert OR Error.

The screenshot shows a filter configuration interface. At the top, there are two buttons: 'And' (selected) and 'Or'. Below this, a rule is configured: 'Submitted to' is 'Submit point 1'. A second rule is added, also with 'And' and 'Or' buttons. The first sub-rule is 'Status' is 'Alert', and the second sub-rule is 'Status' is 'Error'.

6. If required, repeat step 5 until you have configured all rules you need.

7. Click **Apply** or **Apply and save** as required.

The newly created filter is displayed in the blue navigation area on the left and in the upper part of the screen as a blue label. The label indicates that the filter is applied; to stop filtering the jobs, simply click the cross icon in the label. The filter remains available for later use in the navigation area.

2.6.4.4. Managing custom filters

This topic explains how to handle the **custom** filters in the Check jobs view on the Switch Web Portal.

The filters are listed in the blue navigation area below the pre-configured filters.

- To create a new filter, in the blue navigation area, click **+ Create filter**.
Refer to [Creating a custom filter](#) on page 46.
- To edit a custom filter, click the pencil button  beside the filter name.
Refer to [Creating a custom filter](#) on page 46.
- To apply a filter, simply click the filter name in the blue navigation area. The filter will be applied immediately, and you'll see the filter name appear in a blue label just above the jobs overview.
- To stop applying a filter, click the filter name once more (so it's no longer highlighted) or click the cross button in the label.

- To remove a custom filter permanently, in the navigation area, click the cross button beside the filter name. 

2.6.5. Reviewing and processing jobs through the Switch Web Portal

Checkpoints are intermediate folders in a flow where jobs that arrive are being held until they are reviewed by an operator. Once reviewed, the operator indicates how they should move along the flow.

You can review these jobs one by one, or in batch as described below.

2.6.5.1. Processing one job at a time

To review a job being held in a Checkpoint:

1. In the Switch Web Portal, click  to expand the navigation area as required.
2. In the navigation area, click **Check jobs**.
All jobs that you have access to, regardless of their status, are displayed in the overview. The counter indicates the number of jobs that are waiting in a Checkpoint, so all jobs with the 'alert' status.
3. Click **Alert jobs**.
This is a pre-configured filter.
The selected filter is highlighted in the navigation area and applied immediately. In the overview, you will see all jobs that arrive in the Checkpoints you have access to. Remember that you can switch between table and grid view as required (buttons at the bottom of the screen).
4. Select the job you want to review and route:
 - In table view: Double-click the job concerned.
 - In grid view: In the job card of the job concerned, click the **Process** button.
 A dialog opens and displays more detailed information about the selected job.
5. Review the job as required, using the buttons in the top left corner of the dialog.
For an overview, refer to [Review options](#) on page 50.
6. Enter extra info ("metadata") if requested.
This depends on the setup in Switch.



Note: If you entered metadata before locking or replacing a job, you will be requested to enter it again.

7. Route the job:
 - If you see radio buttons, choose one of the options.
 - If you see checkboxes, you can select more than one option if appropriate.
8. Click **Push**.

The dialog is closed automatically. The job will move along the chosen connection(s) in Switch. The job status will change over 'processing' to 'completed', so it will no longer be present in the Alert jobs overview.

2.6.5.2. Processing multiple jobs as one

This topic explains how you can process a number of alert jobs in one go.

Note that this is only possible for:

- Alert jobs waiting in the same Checkpoint,
- Which all need to be moved along the same output connection,
- With the same metadata values.

To process multiple jobs proceed as follows:

1. In the Switch Web Portal, click  to expand the navigation area as required.
2. In the navigation area, click **Check jobs**.
All jobs that you have access to, regardless of their status, are displayed in the overview. The counter indicates the number of jobs that are waiting in a Checkpoint, so all jobs with the 'alert' status.
3. Click **Alert jobs**.
This is a pre-configured filter.
The selected filter is highlighted in the navigation area and applied immediately. In the overview, you will see all jobs that arrive in the Checkpoints you have access to. Remember that you can switch between table and grid view as required (buttons at the bottom of the screen).
4. In the Check jobs area, with the Alert jobs filter selected, click the checkboxes of the jobs you want to combine.
In grid view, the checkboxes become visible when you hover over the job cards. As soon as you have selected a job, the jobs waiting in a different Checkpoint are grayed out, because you can only combine jobs that are waiting in the same Checkpoint.
5. Click **Process multiple** in the bottom right corner of the screen.
The number of jobs contained in the selection is shown.
6. To review the jobs one by one, use the arrows in the top left corner to navigate between them.
For more information about the buttons, refer to [Review options](#) on page 50.
7. Enter extra info ("metadata") if requested.
This depends on the setup in Switch. The metadata value should be valid for all jobs in the selection; it's not possible to have a different value per job file.
8. Route the job:
 - If you see radio buttons, choose one of the options.
 - If you see checkboxes, you can select more than one option if appropriate.

Note that your choice applies to all jobs in the selection.

9. Click **Push**.

The dialog is closed automatically. The jobs will move along the chosen connection(s) in Switch. The job status will change over 'processing' to 'completed', so it will no longer be present in the Alert jobs overview.

2.6.5.3. Review options

This is an overview of the buttons that are available when you're reviewing a job that is held in a Checkpoint.

Some of the buttons may be missing; this depends on the setup in Switch. For example, if editing or report viewing are not allowed, these buttons do not show up.

Option	Meaning
 View	Allows you to view the job file(s). The job is opened in the browser, if the browser supports the job's file type (e.g. PDF, JPEG). If the browser cannot open the file and also in case of a job folder, you will be asked to save the file(s) or folder locally, or they will be downloaded. The behavior depends on your browser settings. When a job is being viewed, it cannot be modified or saved. The job is not locked automatically, so it remains editable for other users, unless you lock it by clicking the Lock button (see further).  Note: You may have to turn off pop-up blockers.
 Save	Allows you to save the job locally. In case of a job folder, the job folder content is compressed and you can download the zip file.
 Replace	Allows you to replace the current job file with another one. The uploaded file(s) will be further moved along the Switch flow.  Note: If another user is trying to replace the job at the same time, a warning is displayed. You can then either cancel your replacement request or overrule the other user's replacement process and start your own. This can be useful if the other user has left the computer in the middle of a replacement request and cannot be reached, or in case of a system crash.
 Report	Allows you to view a report with metadata, if there is one associated with the job. For more information, refer to the documentation on Checkpoints in the Switch Reference Guide.
 Lock / Unlock	Lock: Allows you to lock the job, so that the job (and the report) cannot be processed, edited, reverted or replaced by any other user. Other users can still view the job, save a local copy and open the individual job card, but they will get a message stating that the job is in use by another user.

Option	Meaning
	Unlock: Allows you to unlock jobs you have locked yourself.  Note: Users that belong to the administrator group can unlock all jobs; group managers can unlock all jobs from users in their group.
 Edit in (application)	Allows you to edit the job file in the native application. While a job is being edited, following buttons are displayed: : to upload the changed job file : to cancel editing For the full procedure, refer to Editing a job in a Checkpoint (Switch Helper) on page 51.  Note: This option is only available if you have installed the Switch Helper (a small tool that you can download from the the Enfocus website). If you haven't, you can also edit the job file, but you'll first have to download and save it locally. Refer to Editing a job in a Checkpoint (no Switch Helper) on page 51.

Editing a job in a Checkpoint (Switch Helper)

If you have installed the Switch Helper (a small tool that you can download from the [the Enfocus website](#)), you'll have an **Edit <in application>** button.

To edit a job

1. Click the **Edit** button .
The file is opened in the native application, for example Adobe Acrobat. The **Edit** button on the Portal is replaced with an **Update**  and a **Cancel** button .
2. Make the required changes.
3. Save the file in the native application.
4. Click the **Update** button  to upload the changed version.

Editing a job in a Checkpoint (no Switch Helper)

This procedure is applicable if you're using Switch 2017 or if you haven't installed the Switch Helper application.

To edit a job

1. Lock the job file(s), so no one else can make changes while you're busy with the file.
2. Save the job locally.

3. Make the required changes to your local copy.
4. Use the **Replace** button  to upload the changed version.